

Instructions for loading an UPDATE for the KEMPER 'Control-plus' Hand-held measuring instrument control program Figure 138 00 002



KEMPER 'Control-plus' Hand-held measuring instrument
Figure 138 00 002

The hand-held measuring instruments supplied by KEMPER can come in various software versions. If you want the latest software, please download it from the KEMPER homepage at www.kemper-olpe.de from the section **KEMPER valves, Download data service /Bill of Materials, Product software.**

KEMPER Unternehmen KEMPER Armaturen KEMPER Guss KEMPER Bänder Kontakt

KEMPER

KEMPER Produktsoftware zum Download

Suche

Startseite
Aktuelles & Produktneuheiten
Roßgussarmaturen 'Weser'
Edelstahlarmaturen 'Niro'
Programmergänzungen
Seminare
KEMPER Dendrit CAD
Download Prospekte
Download Datenservice / Ausschreibungstexte
> Ausschreibungstexte
> Datenservice
> Infomaterial anfordern
> Produktsoftware
Online-Katalog / Technische Daten
Kontakt

KEMPER HOTLINE
Noch Fragen?
Tel. 0 27 61-8 91-0
Fax 0 27 61-8 91-1 75
> info@kemper-olpe.de

NEWSLETTER
Name
E-Mail

KEMPER 'Control-plus' Handmessgerät Figur 138 00 002

- > [Gerätesoftware](#)
- > [Auslesesoftware](#)
- > [CPU-Flasher für KEMPER 'Control-plus' Handmessgerät Figur 138 00 002](#)
- > [Anleitung zum Laden eines UPDATE für das Steuerungsprogramm des KEMPER 'Control-plus' Handmessgerät](#)

* zur Übertragung der Daten wird das KEMPER KHS-USB-Adapterkabel Figur 686 02 016 benötigt.

Then decide which software you want to download.

- **Device software or**
- **read-out software**

Unzip the software selected and start with **setup.exe** as described in 1.

A list of the latest extant software versions with the respective date follows:



Device software: V1.06 of 28/04/2011

Read-out software: V1.05 of 28/04/2011



The change history can be viewed in the read-out software in the "Help" section.
All program software versions are included.

This quick reference guide describes how to apply an update of the controller program to the KEMPER 'Control-plus' Hand-held measuring instrument Figure 138 00 002


1. Start Setup. exe and install the required KEMPER CPU flasher program.



2. The KEMPER CPU flasher program opens.





3. Connect the hand-held measuring instrument to the PC, USB adapter cable Figure 68602016




USB cable
Included in the scope of delivery of the
Hand-held measuring instrument


4. Gerätesoftware von der Homepage laden und das hex-file unter Eigene Dateien speichern.
5. Pos.1 Serielle Schnittstelle durch betätigen der Schaltflächen COM Ports und FTDI USB automatisch zuweisen.
6. Pos.3 Gespeicherte aktuelle Gerätesoftware als hex-file unter Eigene Dateien öffnen.



7. Pos .4 Flash the controller with the new software



8. Wait until the loading process has finished. Wait for the message: Flash described



9. The hand-held measuring instrument will restart after the new update. The new version number will be shown in the display during start up. The process is subsequently completed.